Lecture 6 Advanced MATLAB: Data and File Management

Matthew J. Zahr

CME 292 Advanced MATLAB for Scientific Computing Stanford University

22nd April 2014




Announcements

- Homework 1 Graded
 - Feedback uploaded to Coursework
- Homework 2 due today
 - Email me if you need an extension
 - If I don't receive any extension requests, I will post solutions tomorrow
- Homework 3 uploaded; Due next Tuesday
- Lecture 6 of 9



Homework 1 Problem Selection





CME 292: Advanced MATLAB for SC Lecture 6

1 Search Path

2 Import/Export Data

- Text Files
- Low-Level File I/O
- Spreadsheets
- Images

3 Operating System



Outline



2 Import/Export Data

- Text Files
- Low-Level File I/O
- Spreadsheets
- Images





MATLAB Search Path

- Search path is a subset of all folders on the file system that MATLAB uses to efficiently locate files used with MathWorks products. All files in the folders on search path can be accessed by MATLAB.
- Order of folders on search path is important
 - When files in different folders (both in search path) with same filename exist, MATLAB uses the one in the folder nearest the top of the search path
 - Search path includes
 - Folders provided with MATLAB and other MathWorks products
 - MATLAB userpath (first on search path above folders supplied by MathWorks)
 - View entire *ordered* search path: path



Search Path Commands

Command	Description
addpath	Add folders to search path
rmpath	Remove folders from search path
path	View or change search path
savepath	Save current search path
userpath	View or change user portion of search path
genpath	Generate path string
pathsep	Search path separator for current platform



Text Files Low-Level File I/O Spreadsheets Images

Outline



2 Import/Export Data

- Text Files
- Low-Level File I/O
- Spreadsheets
- Images





Text Files Low-Level File I/O Spreadsheets Images

Text File Commands

Command	Description
importdata	Load data from file
dlmread	Read ASCII-delimited file of numeric data into matrix
dlmwrite	Write matrix to ASCII-delimited file
textscan	Read formatted data from text file or string
type	Display contents of file



Text Files Low-Level File I/O Spreadsheets Images

dlmread

- Reads numeric data from the ASCII delimited file
 - RESULT = dlmread(FILENAME)
 - Delimiter *inferred* from file format
 - RESULT = dlmread(FILENAME, DELIMITER)
 - Delimiter specified by string DELIMITER (tabs are '\t')
 - RESULT = dlmread(FILENAME, DELIMITER, R, C)
 - R, C specify the row/column in file of upper left corner of data (zero-based)
 - RESULT = dlmread(FILENAME, DELIMITER, RANGE)
 - RANGE = [R1,C1,R2,C2] specifies upper left and lower right corners of data (zero-based)
- When a delimiter is inferred from the formatting of the file, consecutive whitespaces are treated as a single delimiter. By contrast, if a delimiter is specified by the DELIMITER input, any repeated delimiter character is treated as a separate delimiter.

Text Files Low-Level File I/O Spreadsheets Images

dlmwrite

- Write numeric data in delimited format to ASCII file
 - dlmwrite(FILENAME,M)
 - $\bullet\,$ Write matrix ${\ensuremath{\mathbb M}}$ to file, delimited by ,
 - If FILENAME exists, it will be overwritten
 - dlmwrite(FILENAME, M, DELIMITER)
 - Delimiter specified by string DELIMITER (tabs are '\t')
 - dlmwrite(FILENAME, M, DELIMITER, R, C)
 - R, C specify the row/column in file of upper left corner of data (zero-based)
- Force dlmwrite to append to existing file by using the '-append' flag
- Additional attributes that given to dlmwrite that will alter the format of the ASCII file
 - 'delimiter', 'newline', 'roffset', 'coffset', 'precision'



Text Files Low-Level File I/O Spreadsheets Images


Assignment

- Use dlmread to read the data from all 5 files in the directory liftdrag
- Each file contains the lift-drag history for the flow around the Ahmed body, a bench problem in the automotive industry
- The time history in each file corresponds to a different method of solving the CFD problem
- $\bullet\,$ On the same axes, plot the $f\!i\!f\!t\!h\,$ column of each file vs. the $second\,$ column
 - This is the drag history (drag vs. time)



Text Files Low-Level File I/O Spreadsheets Images

Assignment





Text Files Low-Level File I/O Spreadsheets Images

Low-Level File Commands

Command	Description
fclose	Close one or all open files
feof	Test for end of file
ferror	Information about file IO errors
fgetl	Read line from file, remove newline
	character
fgets	Read line from file, keep newline character
fileread	Read contents of file into string
fopen	Open file
textscan	Read formatted data from text file or string



Text Files Low-Level File I/O Spreadsheets Images

Low-Level File Commands

Command	Description
fprintf	Write data to text file
fread	Read data from binary file
frewind	Move file position indicator to beginning of open file
fscanf	Read data from text file
fseek	Move to specified position in file
ftell	Position in open file
fwrite	Write data to binary file



Text Files Low-Level File I/O Spreadsheets Images

Open/Close File

- FID = fopen(FNAME)
 - Opens the file FNAME
 - FID is a scalar integer valued double, called a file identifier
 - Use FID as the first argument to other file IO routines
 - If fopen cannot open the file, it returns -1
- FID = fopen (FNAME, PERMISSION)
 - Opens the file FNAME in the mode specified by PERMISSION
 - open for reading (r), writing (w), appending (a) create if file does not exist
 - $\bullet\,$ open for reading (r+), writing (w+), appending (a+) do not create file
- ST = fclose(FID)
 - Closes the file associated with file identifier FID, obtained from fopen
 - fclose('all') closes all open files except standard input, output, and error





Text Files Low-Level File I/O Spreadsheets Images

Read line from file (fget1, fgets)

- TLINE = fgetl(FID)
 - Returns the next line of a file associated with file identifier FID as a MATLAB string (identifier incremented)
 - Line terminator is NOT included

• TLINE = fgets(FID)

• Same as fget1 with line terminator included

```
fid=fopen('lec06_ex.m');
  while 1
    tline = fgetl(fid);
    if ¬ischar(tline), break, end
      fprintf(tline)
  end
fclose(fid);
```

• What happens with fgetl replaced with fgets in the above code?





Text Files Low-Level File I/O Spreadsheets Images

Write to text file (fprintf)

- fprintf(FID, FORMAT, A, ...)
 - Applies the FORMAT to all elements of array A and any additional array arguments in column order, and writes the data to a text file with file identifier FID from fopen
 - Set FID to 1 to print to the screen (or exclude)







Text Files Low-Level File I/O Spreadsheets Images

Conversion Characters (fprintf)

Conversion	Value Type
%d,%i	Signed integer
%u	Unsigned integer
%f	Floating point, fixed notation
%e	Floating point, exponential notation (e)
%E	Same as e using E
%g	Compact form of e
%G	Compact form of E
°℃	Single character
%S	String of characters

>> v = 0.333;

>> fprintf('%f,%e,%E,%g,%G\n',v,v,v,v,v)
0.333000,3.33000e-01,3.330000e-01,0.333,0.333



CME 292: Advanced MATLAB for SC Lecture 6

Text Files Low-Level File I/O Spreadsheets Images

Special Characters (fprintf)

Character	Meaning
1.1	Single quote (')
900 100	Percent sign (%)
∖n	Newline
\t	Tab

```
>> fprintf('''Example''\t1%%\n')
'Example' 1%
>> fprintf('Example 2')
Example 2>>
```



Text Files Low-Level File I/O Spreadsheets Images

feof, ftell, frewind, fseek

Consider the command FID = fopen (FNAME). Then,

- ftell(FID) returns the *position* in the file
- fseek (FID, OFFSET, ORIGIN) repositions the file position indicator to the byte with the specified OFFSET relative to ORIGIN
- frewind (FID) resets FID to the beginning of the file FNAME
- feof(FID) returns true if end-of-file indicator has been set

Demo: lec06_ex.m



Text Files Low-Level File I/O Spreadsheets Images

Writing/reading binary files (fwrite, fread)

- count = fwrite(FID,A)
 - Writes the elements of matrix A to the specified file
 - The data are written in column order
 - COUNT is the number of elements successfully written.
- A = fread(FID)
 - Reads binary data from the specified file and writes it into matrix A
 - Reads the entire file and positions the file pointer at the end of the file
- A = fread(FID,SIZE)
 - Reads the number of elements specified by SIZE
 - Valid entries for SIZE are:
 - N read N elements into a column vector
 - inf read to the end of the file
 - [M, N] read elements to fill an M-by-N matrix, in column order (N can be inf, but M can't)

Text Files Low-Level File I/O Spreadsheets Images

textscan

- Read formatted data from text file or string
 - C = textscan(FID, 'FORMAT', N)
 - Reads data from the file, using the FORMAT (recall conversion characters: %u, %i, %u, %f, %e, %E, %g, %G, %c, %s) N times, where N is a positive integer
 - To read additional data from the file after N cycles, call textscan again using the original FID
 - Useful when format of file not uniform through the end of the file



Text Files Low-Level File I/O Spreadsheets Images

Example

Node/element files from UC Berkeley Computer Graphics group. First line of each file contains header information (number of nodes/elements, etc). Nodes contained in columns 2 - 4 for nodes file. Elements contained in columns 2 - 5 of elements file.

```
% UC Berkeley Graphics group mesh format
fname = 'meshes/dragon';
fid = fopen([fname,'.node']); fgetl(fid);
nodes = textscan(fid,'%d %f %f %f %d');
p = [nodes{2:end-1}]; fclose(fid);
fid = fopen([fname,'.ele']); fgetl(fid);
elems = textscan(fid,'%d %d %d %d %d');
t = [elems{2:end}]; fclose(fid);
```

Text Files Low-Level File I/O Spreadsheets Images


Assignment

- Extract the (surface) mesh in the FRG format ('meshes/AGARDwtt.top') into two matrices
 - p $n_v \times 3$ matrix contain xyz coordinates of each node
 - t $n_e \times 3$ containing node numbers of each element comprising a triangle
- FRG file format
 - Line 1: Node header (ignore)
 - Lines 2 $n_v + 1$: [node number, x-coord, y-coord, z-coord]
 - Line n_v+2 : Surface element header (ignore)
 - Line n_v+3 $n_v + n_e + 3$: Last 3 entries per row contain node number of given triangle
- Use simpplot (p,t) to plot the mesh. What is it?



Text Files Low-Level File I/O Spreadsheets Images

Example/Assignment





Text Files Low-Level File I/O Spreadsheets Images

Spreadsheet Commands

Command	Description
xlsfinfo	Determine if file contains Microsoft Excel spreadsheet
xlsread	Read Microsoft Excel spreadsheet file
xlswrite	Write Microsoft Excel spreadsheet file



Text Files Low-Level File I/O **Spreadsheets** Images

Read from Spreadsheets

- [NUM, TXT, RAW] =xlsread(FILE, SHEET, RANGE)
 - Reads the data specified in RANGE from the worksheet SHEET, in the Excel file specified in FILE.
 - The full functionality of xlsread depends on the ability to start Excel as a COM server from MATLAB.
- [NUM,TXT,RAW]=xlsread(FILE,SHEET,RANGE,'basic')
 - Uses basic input mode. This is the mode used on UNIX platforms as well as on Windows when Excel is not available as a COM server.
 - In this mode, xlsread does not use Excel as a COM server, which limits import ability.
 - Without Excel as a COM server, RANGE will be ignored and, consequently, the whole active range of a sheet will be imported.
 - Also, in basic mode, SHEET is case-sensitive and must be string.

Text Files Low-Level File I/O Spreadsheets Images

Write Spreadsheets

- [STAT, MSG] = xlswrite(FNAME, M, SHEET, RANGE)
 - Writes the data in matrix M to the file FNAME in the sheet specified by SHEET to the range of cells specified by RANGE
 - SHEET can be numeric specifying worksheet index or quoted string
 - RANGE is of the form 'X:Y' where X indicates the upper left corner of the writable range and Y is the lower right corner (i.e. 'B2:D4' is the 3 × 3 block of cells from row B to D and columns 2 to 4)
- Requires ability to use Excel as COM server; otherwise, saves to CSV file



Text Files Low-Level File I/O Spreadsheets Images

Image IO Commands

Command	Description
imfinfo	Information about graphics file
imread	Read image from graphics file
imwrite	Write image to graphics file

- A = imread(FILENAME,FMT)
 - Reads a grayscale or color image from the file specified by the string FILENAME in the FMT format
- imwrite (A, FILENAME, FMT)
 - Writes the image A to the file specified by FILENAME in the format specified by FMT
 - For grayscale, A is $m \times n$
 - For colorscale, A is $m \times n \times 3$
- Example: get_rgb.m from Homework 2
- Demo: lec06_ex.m



Outline

1 Search Path

2 Import/Export Data

- Text Files
- Low-Level File I/O
- Spreadsheets
- Images





Operating System Commands

Command	Description
clipboard	Copy/paste strings to/from sys clipboard
computer	Information about computer
dos	Execute DOS command and return output
getenv	Environment variable
perl	Call Perl script
setenv	Set environment variable
system	Execute operating system command and
	return output
unix	Execute UNIX command and return output
winqueryreg	Item from Windows registry
bang (!)	Shell escape

System Calls

- Power of operating system available inside MATLAB
- Given stand-alone C/C++/Fortran code with files defining inputs and outputs
 - Ability to call executable from within MATLAB
 - Use MATLAB's file management to write input files and read output files
 - Provides *non-intrusive* alternative to integrating stand-alone code with MATLAB via MEX interface (Lecture 7)
 - Example: PDE-constrained optimization
 - Given executable that solves some PDE given text file input file and writes solution to binary files
 - Write optimization functions (objective, constraints, derivatives) that: write input files, use system to call executable, read binary outputs, and evaluate function
 - Call fmincon with optimization functions



Systems Calls - Syntax

• [status, result] = SYSTEM('command')

• Calls upon the operating system to execute the given command. The resulting status and standard output are returned.



System Calls - Demo

- Demo: SDESIGN
- Opportunity to dig deeper in homework

